

Email configuration in SAM PuttLab


To send emails directly from the SAM PuttLab software a valid email account has to be configured in the email settings.

To do this go to the Program Settings and then to section “Email (Report)”:



Measurement / Calibration
General
Software Registration
Backup / Restore Data
Program Help
Email (Report)
Report Logo
Video
Still Images
Fitting Protocol
Data Export

In the settings page click the option: “Directly send emails from PuttLab (SMTP)”



Then press the button “Configure SMTP”

In the following dialog all relevant email account settings have to be entered.

The account settings come from your email provider, at least you need to know your user name (in most cases this is just the full email address) and your password.

Email Account Settings

Enter your email account data for sending emails (SMTP):

SMTP Server settings

Host/Server:

User (full email):

Password:

Server Port:

Authentication type:

Sender information

Name:

To make it easier for you to use this configuration form the data for the most common email providers is listed in the table below:

Email Provider	Host/Server	Server Port	Authentication Type
Google (Gmail, Goglemail)	smtp.gmail.com	587 or 465	StartTLS SSL/TLS
Hotmail	smtp-mail.outlook.com	587	StartTLS
Outlook.com	smtp.live.com	587	StartTLS
iCloud.com	smtp.mail.me.com	587	StartTLS
AOL	smtp.aol.com	587	StartTLS
me.com	smtp.mail.me.com	587	StartTLS
Yahoo	smtp.mail.yahoo.com	587	StartTLS
Comcast	smtp.comcast.net	587	StartTLS
Mail.com	smtp.mail.com	587	StartTLS

For Goglemail the following option in Google settings needs to be set: **Allow less secure apps** needs to be switched on.

This can be done with this link when you are logged in to Google:

<https://myaccount.google.com/lesssecureapps?pli=1>