

Activation of a different or new Base Unit in the SAM PuttLab software



Be sure to have the software key for the new base unit available!




Into Base Unit




Into Notebook/PC

1. Connect the USB cable of the new Base Unit to the PC/Laptop using the USB cable.

Setup ?




2. Start the SAM PuttLab software
3. Go to "Setup" and "Registration" in the main menu.



In the Registration-Information window you see all registered software keys / units. In the most cases this would just be one unit.


4. Press the "Add registration" button.

Activation of a different or new Base Unit in the SAM PuttLab software




☞ A new window will open with input fields for the 16 digit software key.

5. Please enter the new key, be careful not to mix up numbers and letters.
6. Press "OK" button to continue.



☞ If the new key is accepted you will now see the registration in the "Available Registrations" list.

7. Highlight the new registration by clicking the line with the mouse (should be blue highlighted after selection).
8. Press "Set as active registration" button.
9. Press "OK" in the registration dialog and again start a measurement or training to check if the registration process was successful.



Delete registration for old unit

If the new unit was a replacement for the old unit and you'll only work with the new one, the old registration can be deleted:

- Select the line with the old unit/key in the "Available Registrations" list.
- Press "Remove registration" button.
- Press "OK"



You cannot remove the only registration, as it would leave your software without valid license!



If you are still not successful with the registration, contact us under:
support@scienceandmotion.com